

## Windows Print File Downloader Installation and Removal Instructions ReadMe

This ReadMe file contains instructions for installing the print file downloader (PFD) on Windows systems. The PFD provides the user interface to download PostScript, PDF, TIFF, and PCL print-ready files and to specify the print features for these files. You must have a printer installed on your system to print files using the PFD.

The PFD can be installed on the following operating systems:

- Windows 2000
- Windows XP
- Windows Vista

The procedure for installing the PFD is the same for all supported operating systems. This procedure assumes that you have a zip program installed on your system. Before proceeding, verify with your Windows administrator that you have the appropriate privileges to install the PFD.

### ***To install the print file downloader:***

1. Close all open applications.
2. Do one of the following:
  - If you are using the Printer Drivers, PPD Files, and Print File Downloader Software CD to install the print file downloader, open the ReadMe.html file and follow the instructions.
  - If you are not using the CD, download and save the .zip file to a folder on your Hard Drive, and continue with this procedure.
3. Navigate to the folder into which you saved the .zip file.
4. Double-click PFDW32\_<language>\_<brand>\_xxxx.zip.  
A window appears and displays the contents of the zip file.
5. Extract the files to a folder on your Hard Drive.
6. Close the zip program.
7. Navigate to the folder into which you extracted the files.
8. Double-click Setup.exe.  
The Welcome to the InstallShield Wizard window appears.
9. Click Next.  
The License Agreement window appears.
10. After reading the license agreement, click Yes to accept the license agreement.  
A second License Agreement window appears.
11. After reading the license agreement, click Yes to accept the license agreement.  
The Choose Destination Location window appears.

*NOTE: Click Browse to change the destination folder, if necessary.*

12. Click Next.  
The Select Features window appears and displays a list of languages.
13. Select the language to install.
14. Click Next.  
The Ready to Install the Program window appears.

15. Click Install.  
After the application is installed, the InstallShield Wizard Complete window appears.
16. Click Finish.  
The PFD is ready to be used.

### **Removing the print file downloader**

The procedure for removing the print file downloader is different for each of the supported operating systems.

#### ***To remove the print file downloader from a Windows 2000 system:***

1. Select Start > Settings > Control Panel.  
The Control Panel window appears.
2. Double-click Add/Remove Programs.  
The Add/Remove Programs window appears.
3. Select the PFD.
4. Click Change/Remove.  
The Confirm Uninstall message appears.
5. Click OK to continue the removal.  
After the files are removed, the Uninstall Complete window appears.
6. Click Finish.
7. Close the Add/Remove Programs window.
8. Close the Control Panel window.

#### ***To remove the print file downloader from a Windows XP system:***

1. Select Start > Control Panel.  
The Control Panel window appears.
2. Double-click Add or Remove Programs.  
The Add or Remove Programs window appears.
3. Select the PFD.
4. Click Remove.  
The Confirm Uninstall message appears.
5. Click OK to continue the removal.  
After the files are removed, the Uninstall Complete window appears.
6. Click Finish.
7. Close the Add or Remove Programs window.
8. Close the Control Panel window.

***To remove the print file downloader from a Windows Vista system:***

1. Select Start > Control Panel.  
The Control Panel window appears.
2. Select Control Panel Home, if necessary.
3. From the Programs list, select Uninstall a program.  
The Uninstall or change a program window appears.
4. Select the PFD.
5. Click Uninstall.  
The Confirm Uninstall message appears.
6. Click OK to continue the removal.  
After the files are removed, the Uninstall Complete window appears.
7. Click Finish.
8. Close the Uninstall or change a program window.

**Establishing Connectivity within the print file downloader to the Printer**

You can connect the PFD to a specific printer using existing Printer Drivers that are installed on your system. At least one Printer Driver must be installed on the local system in order for the PFD to access it and submit a print job.

The PFD uses the selected Printer Driver to submit a print-ready file to the port that is assigned to the Printer Driver. The PFD displays the selectable Printer Drivers in a list in the General tab. The selected Printer Driver itself has no effect on the print job that the PFD submits.

Printer Drivers and PPDs are provided which may be installed on the system to serve this purpose, although any installed Printer Driver will function correctly.